

HALO-X SOFTWARE UPDATE INSTRUCTIONS


NOTE: This update is only available for Windows PC.

Updating software for HALO-X thermal weapon sights (model HALO-X, HALO-X35, and HALO-XRF) requires installing the HALO-X Update Software on Windows 10 PC and Installation of the software on the Halo-X.

IMPORTANT: write down zeroing settings and numbers before updating the software. Zeroing information will be lost after the update.

STEP 1: INSTALL HALO-X UPDATE SOFTWARE ON WINDOWS 10 PC

1. Download the latest **HALO-X Update Software** from the Downloads section on the corresponding product page.
2. Download **Update File** appropriate for your HALO-X scope from the Downloads section on the corresponding product page.
3. Extract the software update file from the zip archive. Locate the file called, for example, **HALO_X_Update_SW_Sept_13_2021.exe** or similar.
4. Extract the Update File. Notice the location where the file with extension .halox was extracted. The file name should look similar to **Halo_XRF_v2_39_05.halox**.
5. Right-click on extracted .exe file (in our example **HALO_X_Update_SW_Sept_13_2021.exe**) and select **Run as Administrator** to install the software update application.




You will be prompted for the Administrator's password if you use Windows under the regular user account. Enter Administrator's password if required.

6. You may or may not get the following warning:




If you get this warning, click on **More info**.

The following window will appear:




Click on **Run anyway**.

7. Confirm installation location and click **Install**:




8. Depending on your computer configuration, you may or may not get the following message during the installation:



If you get this message, click on **Install**.


9. Once install is completed, click **Close**:



10. After successful installation, the shortcut to the HALO-X software will be placed on the Desktop as **halox_update**. It can also be found under **Start Menu -> N-Vision Optics -> halox_update**.


STEP 2: INSTALL THE SOFTWARE ON THE HALO-X

1. Ensure that your 18650 rechargeable batteries are fully charged.
2. Make sure that the HALO-X is **not** connected to the PC via the USB cable.
3. Install batteries and turn on your scope.
4. Verify that the Wi-Fi and LRF are OFF. Turn them OFF if necessary.
5. Enter the Main Menu, select System, then select Update Software.
6. You will see the message: **Update Software Yes/No?**
Choose **Yes** and press the Power button to select.
7. You will see the message: **CONNECT TO PC VIA USB TO COMPLETE SOFTWARE UPDATE**
8. Connect the unit via the USB cable (included with your unit) to the computer.
9. Find **halox_update** on the Desktop or under **Start Menu ->N-Vision Optics -> halox_update** and open the program. You will see the following window:




Click on **Update Halo-X**.

10. You will see a confirmation dialog:




Click **Yes**.

11. You will be prompted to select the Update File next. Go back to the file location where you extracted the **Update File** with the extension **.halox**. Select the appropriate file, for example, **Halo_XRF_v2_39_05.halox**, and click **Open**:



12. Once the update is complete (it takes some time), you will see a message **Update Successful**:



13. Click OK. Your unit is automatically turned off after the update is complete.

14. Close HALO-X Update application.
15. Disconnect the USB cable.
16. Turn on your Halo-X and verify that everything looks and works, as expected.